cs 521: Systems Programming Bit Manipulation

Lecture 21

Bit Manipulation

- Last class, we lightly discussed using the raw bits from a number to determine the mining "difficulty"
 - In C, we deal with numbers at the bit level quite a **bit**(ha!
- They are also frequently used with **flags** to toggle options and combine them with other options
- These are called **bit fields**



- You've already used bit fields
 - Yep! That's right! In two different ways!
- open(file, O_WRONLY | O_TRUNC | O_CREAT, 0666);
 - Here, we are doing a bitwise OR to combine these fields
 - Write only, truncate, and create are all turned on
- They are also supported with struct members
 - Since the layout of a struct varies this is often emulated using a single integer

Another Example: Game Controller

From Wikipedia:

/* Each of these preprocessor directives defines a single bit, corresponding
 * to one button on the controller. Button order matches that of the
 * Nintendo Entertainment System. */

#define	KEY_RIGHT	(1 << 0)	/*	00000001 */
#define	KEY_LEFT	(1 << 1)	/*	00000010 */
#define	KEY_DOWN	(1 << 2)	/*	00000100 */
#define	KEY_UP	(1 << 3)	/*	00001000 */
#define	KEY_START	(1 << 4)	/*	00010000 */
#define	KEY_SELECT	(1 << 5)	/*	00100000 */
#define	KEY_B	(1 << 6)	/*	01000000 */
#define	KEY_A	(1 << 7)	/*	10000000 */

Is the left shift operator; we can also shift to the right: >>

Writing in Binary

The previous example, written directly using **0**^b syntax:

#define	KEY_RIGHT	0b00000001
#define	KEY_LEFT	0b00000010
#define	KEY_DOWN	0b00000100
#define	KEY_UP	0b00001000
#define	KEY_START	0b00010000
#define	KEY_SELECT	0b00100000
#define	KEY_B	0b01000000
#define	KEY_A	0b1000000

Bitwise Operators

- AND(&)
- OR (|)
- NOT (~)
- XOR (^)
- Bit shifting:

>>

- < <

Bitwise AND

Compare the two sets of bits. If both bits are set, the result is a 1 :

```
0101 (decimal 5)
AND 0011 (decimal 3)
= 0001 (decimal 1)
/* C: */
0101 & 0011 = 0001
```

Often used to determine (test) if particular bits are set.

Bitwise OR

If either bit is set to 1, then the result is 1:

```
0101 (decimal 5)
OR 0011 (decimal 3)
= 0111 (decimal 7)
/* C: */
0101 | 0011 = 0111
```

Often used to set (turn on) particular bits.

Bitwise NOT

Flips the bits:

```
NOT 0111 (decimal 7)
= 1000 (decimal 8)
/* C: */
~0111 = 1000
```



Set to 1 if only one of the bits is 1, but set to 0 if both bits are 0 or both are 1:

```
0101 (decimal 5)
XOR 0011 (decimal 3)
= 0110 (decimal 6)
/* C: */
0101 ^ 0011 = 0110
```

Often used for toggling particular bits.

Back to our Game Controller

```
int gameControllerStatus = 0;
/* Sets the gameControllerStatus using OR */
void keyPressed(int key) {
     gameControllerStatus |= key;
}
/* Toggles the gameControllerStatus using XOR */
void keyPressed(int key) {
     gameControllerStatus ^= key;
}
/* Tests whether a bit is set using AND */
int isPressed(int key) {
    return gameControllerStatus & key;
```

Flipping Bits

- Want to toggle a flag?
 - opts = opts ^ flag
- Turn it off?
 - opts = opts & ~flag
- On?
 - opts = opts | flag



You can move bits around with << and >> :

00010111 << 1 = 00101110 00010111 << 3 = 10111000 00010111 >> 1 = 00001011 00010111 >> 3 = 00000010

Neat: A left shift by n is the same as multiplying by 2^n

Hexadecimal

- We use Base 10 for our daily lives
- Computers? Base 2
- And then there's Base 16... Hexadecimal
 - Denoted by 0x
- Hexadecimal is a compact way to represent 4 bits of information
 - 4 bits = nibble
 - 8 bits = byte
- So **0xFF** gives us a byte's worth of information

Hex Notation

- You might've noticed we've been using hexadecimal a lot when working with binary
 - 0-9 : 0-9 in binary
 - A-F : 10-15
 - So, we can store 16 bits of information
- Hex is nice when working with binary numbers:
 - int i = 2815;
 - int i = 0xAFF;
 - 0xAFF = 1010 1111 1111

The Difficulty Mask

- In P3, we start out with a difficulty mask of
 0x00000FFF
- Five 0's and 3 F's, or in binary:
 - 5 * 4 = 20 bits of zeros
 - 3 * 4 = 12 bits of ones

Setting Specific Bits

- Let's say I asked you to set the 3rd bit in a bit field
- How would you accomplish this?
- bit_field = bit_field | (0x1 << 3)</pre>
- We can extend this approach to adjust the difficulty of our bitcoin miner
- We'll just need to find out how many bits we need to to set to 1